- CONNESSIONE AL CLUSTER DA DESKTOP REMOTO

1. Per prima cosa bisogna installare il client sul proprio computer (macOS, Linux, Windows) dal seguente link

https://www.cendio.com/thinlinc/download

N.B. Per installazione su macOS:

- dovrebbe essere sufficiente fare doppio click sull'icona denominata tl-4-14.0_2324-clinet-macos.iso e successivamente trascinare la app nella cartella delle applicazioni,
- in alternativa, il file tl-4-14.0_2324-clinet-macos.iso può essere aperto da terminale con il comando open tl-4.14.0_2324-client-macos.iso.iso

N.B. Per installazione su Linux/UBUNTU:

- dovrebbe essere sufficiente fare doppio click sull'icona
- in alternativa, scaricare il file (deb o rpm) e, da terminale, digitare "sudo apt install nomefile"

2. Una volta installato, doppio click sull'icona,



e si aprirà una finestra come questa

	Client	ThinLinc	
ThinLinc [®]			Versione 4.14.0 Build 2324
Server:	login05.iasfbo.ir	af.it	
Nome utente:	gruppo01		
Password:	******		
Termina sessione	esistente		Opzioni
Esci		Avanzate<<	Connettiti <=
Inserisci nome utente e	password per co	onnetterti.	

ciascun gruppo si collega con lo username e la password del gruppo e poi clicca su **Connettiti**

Seguiranno alcuni passaggi di setup standard:

Thinl	inc Profile Chooser	×
Welcome	to Cendio ThinLinc	
Welcome to your	newly installed ThinLinc system.	
This introduction message is displayed during the profile selection. The message can be customized or disabled as you see fit for your installation. Please see the ThinLinc Administrator's Guide for more information.		
If multiple profiles are available, the " If there is only one available profil command, the "	Forward" button will display a list of avai le, or if the profile selection is overriden b OK" button will start the session.	lable profiles. y a client
If you want to log out at th	is moment, please press the "Ouit" butto	n.
, , , , , , , , , , , , , , , , , , , ,		
	Quit	Forward

cliccare Forward

ThinLinc Profile Chooser			
Welcome to Cendio ThinLinc			
Select a profile below: Screen shot:			
🔘 👸 GNOME Desktop	Anna an an an anna an an an an an an an a		
⊙ 📽 GNOME Classic Desktop	Image: Section 1 Section 2 <t< td=""></t<>		
	Description:		
	GNOME offers an easy to understand desktop for your GNU/Linux or Unix computer. GNOME's focus is ease of use, stability. and first-class internationalisation and accessibility support.		
ThinLinc'	Quit Back OK		

Selezionare 'GNOME Classic Desktop' e premere OK

	gı	ruppo05@login05 - Client ThinLinc			da
Applications Places gnome-initial-set	цр		Tue 10:07		G
		Welcome		Ne	ext
	Deutsch	Deutschland			
	English	United Kingdom			
	English 🖌	United States			
	Español	España			
	Français	France			
	Русский	Российская Федерация			
	العربية	مصر			
	日本語	日本			
	汉语	中国			
		:			
🗗 🔀 gnome-initial-setup					

premere Next

Applications	Places	anome-initial-se	gruppo05@login05 - C	lient ThinLinc	Tue 10:11	ま 心 心
Previous	Tuces	ghome initial se	Typing		100 10111	Next
			Typin Select your keyboard layout	g or an input method.		
			Cameroon Multilingual (Dvorak)	Preview		
			Cameroon Multilingual (QWERTY)	Preview		
			English (Australian)	Preview		
			English (Cameroon)	Preview		
			English (Canada)	Preview		
			English (US)	✓ <u>Preview</u>		
			:			
🗗 🔀 gnome-	-initial-setu	р				

premere Next



mettere **OFF** e poi premere **Next**



Un ultimo passaggio:



premere 'X' per chiudere

L'utente ora è dentro al cluster



può aprire il terminale e iniziare a lavorare. Se non dovesse già apparire l'icona del Terminale:

Applications > System Tools > trascinare icona 'Terminale' sul Desktop

N.B. Se il client dovesse andare in *standby,* per sbloccare basta premere il tasto **Invio** e **mettere la password** del gruppo.

Per uscire cliccare in alto a destra e premere Log out:



Un messaggio di errore tipo

Message from syslogd@login05 at Feb 16 17:30:25 ... kernel:[Hardware Error]: Corrected error, no action required.

Message from syslogd@login05 at Feb 16 17:30:25 ... kernel:[Hardware Error]: CPU:24 (15:1:2) MC4_STATUS[Over|CE|MiscV|-|AddrV|-|-|CECC]: 0xdc76c00020080813

Message from syslogd@login05 at Feb 16 17:30:25 ... kernel:[Hardware Error]: Error Addr: 0x000000c9b7c4000

Message from syslogd@login05 at Feb 16 17:30:25 ... kernel:[Hardware Error]: MC4 Error (node 3): DRAM ECC error detected on the NB. Message from syslogd@login05 at Feb 16 17:30:25 ...

non è un problema, basta premere Invio e proseguire con ciò che si stava facendo.